
Protocol



For 20 sensor, there is a total of 181byte or 1448bit data.

8bit Binary = 00111011 Or ASCII = ; Header Total 8bit		
8bit XXXXXXXX	duration (divide by 50 to get microseconds)	
8bit XXXXXXX	Total 24bit	
8bit 00000XXX	X is Data	
8bits XXXXXXXX	Sensor id	First sensor 72bit
8bits 000000XX	Total 16bit	Tirst sensor 720it
8bit 0000000X	Valid id Total 8bit	
8bit 0000000X	Axis id Total 8bit	
8bit 0000000X	Lighthouse id Total 8bit	
8bit XXXXXXXX	duration (divide by 50 to get microseconds)	
8bit XXXXXXXX	Total 24bit	
8bit 00000XXX	X is Data	
8bits XXXXXXXX	Sensor id	Second sensor 72bit
8bits 000000XX	Total 16bit	Second Sensor 72010
8bit 0000000X	Valid id Total 8bit	

8bit 0000000X	Axis id Total 8bit	
8bit 0000000X	Lighthouse id Total 8bit	
20 sensor		